

Lab 2 IoT Hub + Huzzah

By: Kevin Saye

IoT Solution Architect

December, 2017

This lab assumes you have completed Lab 1.

If you have any issues or concerns, please email: virtualbootcamphelp@microsoft.com.

Execution Time: 30 minutes.

Required Hardware:

- Windows 10 PC
- IoT Hardware kit: https://www.adafruit.com/product/3605 or similar hardware.
- Access to a WiFi network (without a captive portal aka web page login)

Required Operating System:

Windows 10


Other Requirements:

• Azure Subscription


Required Software:

Software	Size	Installation URL
IoT Device	5 MB	https://github.com/Azure/azure-iot-sdk-csharp/releases/download/2017-10-
Explorer		23/SetupDeviceExplorer.msi


Step 1. Go to http://portal.azure.com, click the Plus sign on the left and search for IoT Hub




Step 2. Select the IoT Hub by Microsoft and click Create.




Step 3. Give your hub a unique name, select the correct Azure Subscription, create a new (or use an existing Resource Group) and click create. Change the Pricing and Scale Tier to F1, if available to save cost.



Step 4. Click the Resource Group Icon on the left, select the resource group you just created and click on your IoT Hub just created.




Step 5. Once the Hub is crated (about 2 minutes), click on the Shared Access Policies and then the iothubowner and then the copy icon to copy the connection string to the clipboard and save in a text file. This will be used in the next Lab.




Step 6. If not already installed, install (https://github.com/Azure/azure-iot-sdk-csharp/releases/download/2017-10-23/SetupDeviceExplorer.msi) and run the Device Explorer.


Step 7. Using the connection string copied from step 5, past it in Device Explorer and click Update.




Click the Management Tab and Create. Then type in your device name and click Create.




Next, select your device, right click and copy the device connection string and save it to notepad to be used for our device.




Step 8. Launch Arduino. Add the Microsoft IoT and Arduino libraries by clicking Sketch → Include Library → Manage Libraries and search for "AzureIoT". Install the library AzureIoTHub by Arduino, the AzureIoTProtocol MQTT by Microsoft and AzureIoTUtility by Microsoft, as shown below.




Step 9. Starting with a new sketch and copy the content from: http://tinyurl.com/MayNodeMCU and modify the ssid, pass, and connectionString on lines 18 - 20 as shown below and click the "Compile and Upload" button.




Step 10. Using Device Explorer, click Data, select the correct device and click Monitor. The screen should look something like (calculating the temperature in Celsius):



Step 11. Using Serial Monitor, you can see that messages are successfully sent and we get confirmation from IoT Hub that the message was received:



Step 12. Use Device Explorer, Click Message To Device. Type a message add any desired properties and click send, as shown below:



Step 13. Using Serial Monitor, you can see that the message was received, and any properties:

```
Message Id: 106 Received.

Message Id: 107 Sent.

Message Id: 3fae5aa0-f78e-45f3-91ec-f5b6c077b58b Received. Message: "this is a test", Properties: "myprop=myval," Message Id: 107 Received.

Message Id: 108 Sent.

Message Id: 108 Received.
```

This completes this lab. If time permits, read the setup(), loop() and supporting functions. Note that the temperature is in Celsius, as we will adjust this later.